

## Mercury Payment Systems and PPI Setup

Net EPay Setup

Primary Host Name	x1.mercurypay.com
Secondary Host Name	b2.backuppay.com
Merchant Id Number	494901
Terminal Id	00000
Data Cap Dial Host	

Default Dial    Default Internet    Delete    Save

Net EPay Setup

Primary Host Name	PayMover
Secondary Host Name	PayMover
Merchant Id Number	9EHVE9VB35VH3VB93HV34VB4380VH348C
Terminal Id	00000
Data Cap Dial Host	

Default Dial    Default Internet    Delete    Save

If the customer opts to use Mercury or PPI, this is the way we configure MicroSale. ***This is a built in interface for MicroSale and does not need any additional software to use!*** Go to *Managers Menu/Register Setup/Credit Card Setup*. See the illustration above. “Primary Host Name” and “Secondary Host Name” are automatically set to these values for Mercury by hitting the button “Default Internet”. For PPI type in *PayMover* for the primary and secondary hosts. “Merchant Id Number” is a specific number given the end user by Mercury and PPI and is entered in this field. ***This value MUST be entered exactly as given by Mercury and PPI or this system will not be able to process credit cards properly!*** The number shown in this illustration is the Mercury test number. If this number is entered in, upon starting MicroSale a message will come up “Mercury Test Account in Use”. This is significant, as only a Mercury-supplied test card will work with this account, and it will not accept live credit cards. “Terminal Id” in the Mercury configuration will always be “00000”. Leave “Data Cap Dial Host” blank. Once all these fields have been configured, exit and restart MicroSale to write these values into the Windows registry. ***Note: if for any reason this terminal is logged off and back on as a different user, these fields will all be blank and will have to be re-entered!*** This procedure must be carried out on every MicroSale terminal in the network.

## Mercury Dial Bridge Configuration

There is now a way to use the Mercury interface, but still have a dial backup solution. It is called “IP/Dial Bridge for Mercury”. This is a relatively low cost hardware/software combination that uses a standard Datatran in conjunction with the Dial bridge software obtained from Datacap. The first step would be to install the software (very similar to Dial Epay and Net Epay). An activation code will be needed from Datacap. Then, install the Datatran modem onto an available com port on the terminal that will be acting as the credit card server for the system. This terminal would also need to be in close proximity to an available phone line to enable the Datatran to dial out as needed. The initial setup in MicroSale is similar to Dial E-pay. The button “Default Dial” can even be used. See illustration on next page.

Net EPay Setup

Primary Host Name	Bench
Secondary Host Name	Bench
Merchant Id Number	494901
Terminal Id	00000
Data Cap Dial Host	

Default Dial    Default Internet    **Delete**    **Save**

In the picture at left, we can see that the *Primary Host Name* and *Secondary Host Name* are both “Bench”. Put the network name for the terminal in your network (ours is “Bench”) that is running the Dial Bridge software. It is still necessary to enter the *Merchant Id Number* obtained from Mercury in the proper field. The number shown at left is the Mercury test number.

This is the way every terminal in the MicroSale network that accepts credit cards would be set up (including the backoffice terminal). All of these terminals will process credit cards directly over the internet unless the internet becomes unavailable (for whatever reason). If this happens, the terminals would automatically switch and start processing through the dial-up connection provided by the Dial Bridge software and the Datatran modem.

### **Datacap Credit Card Setup**

As with the Mercury setup, go to *Managers Menu/Register Setup/Credit Card Setup*. This time, push the button “Default Dial” This would change the screen to look like the illustration below:

Net EPay Setup

Primary Host Name	Enter Server Name
Secondary Host Name	Enter Server Name
Merchant Id Number	DialEPay
Terminal Id	00000
Data Cap Dial Host	

Default Dial    Default Internet    **Delete**    **Save**

Notice that “Primary” and “Secondary” host names show “Enter Server Name”. Both these fields would have the name of the MicroSale terminal on the network that has Dial E-pay installed, and is basically the credit card server for the network. This would hold true for every terminal, including the credit card server. “Merchant Id Number” now shows DialEPay. This is the default and doesn’t need to be changed. Once again, “Terminal Id” is all zeros. Leave “Data Cap Dial Host” is left blank. Once the fields have been configured, hit “Save” and exit then restart MicroSale.